


Resizing images with AI in PaintShop Pro

Description

When working with images in PaintShop Pro, you are likely to need to resize them to fit your project. Sizing down has never been a problem but sizing up can be challenging. We would always recommend avoiding sizing up since it would cause blur and loss of quality. But, since version 2021, PaintShop Pro now has a new command: **AI-Resize**.

Where to find that command?

The **AI-Resize** command is in the **Resize** dialog window. Once you open the **Resize** command, by default, you will see this:



In this window, you don't see the **AI-powered** settings so you have to click on the checkbox to make them appear.

By Pixels By Percentage By Print Size Based on One Side

Resize by setting the width and height in pixels.

	Original	New
Width:	1000	<input type="text" value="500"/>
Height:	1000	<input type="text" value="500"/>

<Standard sizes>

Advanced and AI-Powered Settings

Resample using:

Sharpness

Smoother Sharper

Maintain original print size

Lock aspect ratio: to 1

Resize all layers

At this point, you will have the option to choose which resampling mode you want to use. This is where you will see the **AI-Powered** mode appear.

By Pixels By Percentage By Print Size Based on One Side

Resize by setting the width and height in pixels.

	Original	New
Width:	1000	<input type="text" value="500"/>
Height:	1000	<input type="text" value="500"/>

<Standard sizes>

Advanced and AI-Powered Settings

Resample using:

Sharpness Smoother

Maintain original print size

Lock aspect ratio: to 1

Resize all layers

AI-Powered

Bicubic
Smart Size
Bicubic
Bilinear
Pixel Resize
Weighted Average

Once you select the **AI-Powered** resampling mode, notice that the bottom part of the advanced settings is now different.

By Pixels By Percentage By Print Size Based on One Side

Resize by setting the width and height in pixels.

	Original	New
Width:	1000	<input type="text" value="500"/>
Height:	1000	<input type="text" value="500"/>

<Standard sizes>

Advanced and AI-Powered Settings

Resample using: AI-Powered

Mode:

Photorealistic

Illustration

Noise Reduction:

None Maximum

GPU Acceleration

In this illustration, all the settings are greyed out. That is because the settings chosen on top don't indicate that you are sizing UP. Those various options will only be available in that case.

Let's size up

On the top, let's change the settings so that we will enlarge our image. Starting with an initial size of 1000 x 1000 pixels, let's aim for 1500 x 1500 pixels. Immediately, you see those options are now available.

The screenshot shows a software interface for image resampling. At the top, there are four radio buttons: "By Pixels" (selected), "By Percentage", "By Print Size", and "Based on One Side". Below this, a text box says "Resize by setting the width and height in pixels." There are two columns: "Original" and "New". Under "Original", "Width:" and "Height:" are both set to "1000". Under "New", "Width:" and "Height:" are both set to "1500". A lock icon is positioned between the two "New" input fields. Below the "New" fields is a dropdown menu showing "<Standard sizes>".


Below the main settings, there is a section titled "Advanced and AI-Powered Settings" which is checked. It contains a "Resample using:" dropdown set to "AI-Powered". Underneath, there are "Mode:" options: "Photorealistic" (selected) and "Illustration". There is also a "Noise Reduction:" slider ranging from "None" to "Maximum". At the bottom, there is a checked checkbox for "GPU Acceleration".

One thing you will likely notice is that as soon as you enter some values that indicate you are enlarging the image, the **AI-Powered** resampling mode will be set for you by default.

The settings on the bottom might be important for you in special circumstances. If you are enlarging a LOT (like maybe 1000%) but for typical enlargement, those settings have not shown a lot of differences. But it is really up to you to test.

Missing settings?

As mentioned earlier, once you have the **AI-Powered** resampling mode, the settings on the bottom half are different. One particular setting that you might be looking for is the "**Resize all layers**". This could be very useful to use if you want to resize only one layer on a multi-layered project. But where is it? The only way to get that setting back is to temporarily change the resampling mode to something other than **AI-Powered**. Let's change it back to **Bicubic**.



That is where you can check or uncheck the setting. After that, change the resampling mode back to AI-Powered and you will be able to enlarge your image. This little step might be useful to know because if you set the dimension values to enlarge, on the top part of the dialog window, it will automatically select AI-Powered for you. At that point, you will not have the option to check or uncheck the Resize all layers, which might lead to unwanted results.

Enlarging your image will require time and resources, so beware of that. Depending on the starting size of your image and how much you are enlarging it, the process can take a long time, and you might feel like your program froze. Be patient. It will work on its own and you will get a great result.

For more information on resizing the right way, check out [this article](#).

Date Created

January 16, 2023

Author

myclone